


Using a School Chrome Account (Profile) at Home

When you log into a personal computer and open the Chrome browser, you can browse away on whatever Chrome account/profile is logged in, or as a generic user. But you may not be logged in to YOUR Chrome account/profile. To access your school accounts, such as Schoology, your school email, and all the resources in D11 Student Links, you need to be signed into your school Google Account (Profile).

You can tell what Chrome account/profile you are using by looking at the icon in the top right corner. If it is not the generic one, a person's name, initials, or avatar will show there.


Managing Multiple Accounts (Profiles) on the Same Computer



It is easy to set up and manage multiple Google accounts/profiles.

How to Add a New Profile

1. Open **Google Chrome** on your computer.
2. Click your **profile picture** or avatar icon in the top-right corner, next to the web address bar.
3. Select **Add** at the bottom of the pop-up menu.
4. Sign in with the **Google account** you want to use, or choose to continue without signing in.
5. Turn on **Sync** if you want to save bookmarks, history, and passwords for that specific account.
6. Choose a **name, photo, and color theme** so you can easily tell your profiles apart.



How to Switch and Manage Profiles

1. Click your **profile icon** in the top-right corner of any open Chrome window.
2. Select the **other profile** you want to use from the list to open it in a separate window.
3. Click **Manage Chrome profiles** in the menu to edit names, change theme colors, or delete old profiles you no longer need.

How to Create a Desktop Shortcut for a Specific Profile



1. Open **Google Chrome** and switch to the profile you want to create a shortcut for.
2. Click the **Profile Picture** in the top-right corner.
3. Select **Manage Chrome profiles** (the gear icon ).
4. Click the **three dots** (More actions) on the specific profile card and choose **Edit**.
5. Scroll down to the bottom of the settings page and toggle on **Create desktop shortcut**.

How to Show the Profile Selection Screen on Startup

1. Open **Google Chrome**.
2. Click your **Profile Picture** in the top-right corner.
3. Click the **Manage Chrome profiles** gear icon  to open the profile selection window.
4. Check the box next to **Show on startup** in the bottom-left corner of that window.

Video Tutorials

Here are a few short videos on the processes I have described above.

[How to Create Multiple Google Chrome Profiles](#)

[How to Open the Google Chrome Profile Selector](#)

[How to Create Chrome Profiles Shortcut Icons on your Desktop](#)